

COSI Interfaces Definition

Frame Buffer

The input image processed by the OCR agent is mapped as a shared memory area. This allows the client program to export the input image without writing any intermediate image file (which is often a resource consuming process in term of CPU and i/o operations). The shared memory (shmем) frame buffer contains some image format information, followed by the RGB pixels.

Offset	Format	Field name	Content
0	unsigned long (32 bits)	width	Frame width in pixels (number of pixels per row)
4	unsigned long (32 bits)	height	Frame height in pixels (number of rows)
8	unsigned long (32 bits)	bpp	Bytes per pixel. Incrementing a frame buffer pointer (X,Y) by this value makes it point to (X+1,Y)
12	unsigned long (32 bits)	rowstride	Bytes per row. Incrementing a frame buffer pointer (X,Y) by this value makes it point to (X,Y+1).
16	array of bytes	buf[]	Array of pixels. The size depends of the frame geometry fields above (typically height * rowstride).

A C declaration of the shmем frame buffer would then give:

```

struct COSI_frame_buffer {
    unsigned long width;      /* Number of pixels per row */
    unsigned long height;    /* Number of rows */
    unsigned long bpp;       /* Bytes per pixel */
    unsigned long rowstride; /* Bytes per row */
    unsigned char buf[1];    /* Actual size is .height * .rowstride */
};
  
```

In a POSIX operating system (Unix, Linux, BSD and others), a shared memory buffer is designated by a numerical key called a "shmем". The shmем should be given by the client to the OCR agent as an input parameter. The client and the OCR agent should alloc and map the shared frame buffer using the POSIX shared memory system calls (shmget, shmat, etc.).

Requests input


Once the frame buffer is mapped, the OCR agent is ready to accept processing requests from its standard input. An input request is a textual command line, composed of attributes, and terminated by a newline character (Line Feed). Each attribute follows the XML-like *attr-name="attr-value"* format. Quotes may be omitted if *attr-value* does not contain blank characters (space, tab, etc.).

The request format synopsis is:

```
[id=request-id] [geometry=window-geometry] [options...]
```

- ▶ The request can be identified using the "id=*request-id*" attribute. This identifier is an arbitrary text word used as a traceability marker between the request and the output result.
- ▶ The request may contain a "geometry=*window-geometry*" attribute, which is a *Region Of Interest* asking the OCR agent to perform the text extraction from within this window rather than from the full frame buffer area.

The *window-geometry* specification complies to the X-Window (X11) geometry format. This format allows to define the window position and size in a single character string *WxH+X+Y*. *WxH* represents the size of the window, and *+X+Y* represents the position.



- ▶ The other "*options...*" attributes are optional and depend on the OCR agent capabilities and features. Unsupported attributes should be silently ignored by the OCR agent.

Results output

After OCR process is completed, the result are output in XML format. This format shows the extracted text on both a per-character and per-line basis, and includes the localisation information of the character/line objects.

The synopsis of the XML output format follows:

```
<document id="request-id" geometry="window-geometry" options...>
  <page>
    <line geometry="line-geometry">
      <box geometry="box-geometry" value="char" />
      ...
      <space geometry="line-geometry" />
      ...
    </line>
    ...
  </page>
</document>
```

The whole output data are encapsulated into the top-level element `<document>`. The attributes of this element are directly taken from the input request: request identifier, window (ROI) geometry, and other agent-specific options.

Document pages are delimited by elements `<page>`. This element is for future (and well, it also keeps some coherence in the page layout hierarchy) : only one page per document is supported by COSI for now.

Each line extracted from the document is stored in a `<line>` element. The attribute `geometry="HxW+X+Y"` indicates where the line is located.

Inside each `<line>` element are listed the extracted characters. An "real" character is embedded into a `<box>` element, with its geometry and ASCII symbol respectively stored as attributes `geometry` and `value`. A space is not considered as a normal character, but is shown as a `<space>` element, with its geometry as an attribute.

The example below shows an output from the *Tesseract* OCR agent. It extract a piece of text from the sample image *eurotex.tif* (included in the *Tesseract* source tree for testing purpose):

```
<document id="TEXT" geometry="805x117+93+53">
<page>
<line geometry="721x52+11+12" >
<box geometry="28x32+11+12" value="T" />
<box geometry="22x34+42+12" value="h" />
<box geometry="19x25+67+21" value="e" />
<space geometry="25x44+86+12" />
<box geometry="14x40+111+15" value="(" />
<box geometry="22x34+128+22" value="q" />
<box geometry="22x24+153+24" value="u" />
<box geometry="11x33+179+14" value="i" />
<box geometry="20x26+194+22" value="c" />
<box geometry="22x33+216+14" value="k" />
<box geometry="15x38+241+16" value=")" />
<space geometry="26x44+256+14" />
<box geometry="13x41+282+17" value="[" />
<box geometry="23x34+297+17" value="b" />
<box geometry="18x24+322+25" value="r" />
<box geometry="23x26+340+25" value="o" />
<box geometry="31x25+365+26" value="w" />
<box geometry="23x25+399+25" value="n" />
<box geometry="13x41+424+17" value="]" />
<space geometry="28x43+437+17" />
<box geometry="16x40+465+20" value="{" />
<box geometry="21x34+486+18" value="f" />
<box geometry="23x26+503+27" value="o" />
<box geometry="23x23+528+29" value="x" />
<box geometry="16x40+556+19" value="}" />
<space geometry="21x46+572+18" />
<box geometry="16x42+593+22" value="j" />
<box geometry="24x26+612+31" value="u" />
<box geometry="35x25+638+30" value="m" />
<box geometry="24x33+674+30" value="p" />
<box geometry="18x26+700+31" value="s" />
<box geometry="9x35+723+21" value="!" />
</line>
<line geometry="786x54+10+61" >
<box geometry="32x34+10+61" value="O" />
<box geometry="22x24+44+71" value="v" />
<box geometry="20x25+68+71" value="e" />
<box geometry="16x24+91+71" value="r" />
<space geometry="24x37+107+61" />
<box geometry="13x30+131+68" value="t" />
<box geometry="23x33+147+64" value="h" />
<box geometry="20x25+172+72" value="e" />
<space geometry="25x42+192+63" />
<box geometry="20x38+217+63" value="$" />
<box geometry="21x33+241+66" value="4" />
<box geometry="18x33+267+66" value="3" />
<box geometry="9x13+292+92" value="," />
<box geometry="21x32+306+67" value="4" />
<box geometry="20x33+331+67" value="5" />
<box geometry="22x32+355+67" value="6" />
<box geometry="8x8+382+92" value="." />
<box geometry="21x32+396+67" value="7" />
<box geometry="21x33+421+67" value="8" />
<space geometry="26x49+442+63" />
<box geometry="24x24+468+74" value="<" />
<box geometry="11x34+496+68" value="l" />
<box geometry="20x26+511+77" value="a" />
<box geometry="20x24+534+79" value="z" />
<box geometry="22x33+555+79" value="y" />
<box geometry="25x24+580+73" value=">" />
<space geometry="24x38+605+68" />
<box geometry="22x35+629+71" value="#" />
<box geometry="20x33+655+72" value="9" />
<box geometry="22x32+678+73" value="0" />
<space geometry="25x44+700+71" />
<box geometry="22x33+725+74" value="d" />
<box geometry="21x25+750+82" value="o" />
<box geometry="23x34+773+81" value="g" />
</line>
</page>
</document>
```

The (quick) [brown] {fox} jumps!
Over the \$43,456.78 <lazy> #90 dog
& duck/goose, as 12.5% of E-mail
from aspammer@website.com is spam.
Der „schnelle“ braune Fuchs springt
über den faulen Hund. Le renard brun
«rapide» saute par-dessus le chien
paresseux. La volpe marrone rapida
salta sopra il cane pigro. El zorro
marrón rápido salta sobre el perro
perezoso. A raposa marrom rápida
salta sobre o cão preguiçoso.

Bringing COSI support to existing OCR agents

GOOCR

COSI support is available for GOOCR 0.46 and later. It is brought by 3 source patch files, to be applied to the original GOOCR development tree :

- `job.patch` brings a minor modification making GOOCR parse its command arguments in a more efficient manner. In the original approach, the command arguments were parsed in the main processing loop, and parsed again each time a new OCR job is done. In the new approach, arguments are parsed only once at the beginning.
- `xml_output.patch` extends the original XML output capabilities of GOOCR to the COSI format. It adds a command option “-F *num*” (like in XML Filter) to enable COSI-specific attributes and elements. By default, the original GOOCR format (i.e. non-COSI compliant) is enabled).
- `server.patch` adds COSI server capability to GOOCR, by adding support for getting an image from a shared memory frame buffer, and accepting requests from the standard input. This mode is enabled with a new command option “-S *shmid*”.

To invoke GOOCR as a COSI server from a shared-memory frame buffer id *shmid*, the command is:

```
$ gocr -f XML -F 10 -S shmid
```

Tesseract-OCR

COSI support is available for Tesseract 2.03 and later. It is brought by 2 source patch files, to be applied to the original Tesseract development tree :

- `xml_output.patch` brings XML output capabilities to Tesseract, complying to the COSI format. This output format can be enabled by setting the new boolean external variable `xml_output` to TRUE.
- `server.patch` adds COSI server capability to Tesseract, by adding support for getting an image from a shared memory frame buffer, and accepting requests from the standard input. This mode is enabled by setting the new boolean external variable `server_mode` to TRUE.

To invoke Tesseract as a COSI server from a shared-memory frame buffer id *shmid*, the command is:

```
$ tesseract shmid - batch.no chop server
```

GNU Ocrad

COSI support is available for Ocrad 0.19 and later. It is brought by 2 source patch files, to be applied to the original Ocrad development tree :

- `xml_output.patch` brings XML output capabilities to Ocrad, complying to the COSI format. XML output can be enabled with the command option “- -xml”. It is written to the result export file (option “-x *exportfile*”).
- `server.patch` adds COSI server capability to Ocrad, by adding support for getting an image from a shared memory frame buffer, and accepting requests from the standard input. This mode is enabled with a new command option “-S *shmid*”.

To invoke GNU Ocrad as a COSI server from a shared-memory frame buffer id *shmid*, the command is:

```
$ ocrad -x - -xml -S shmid
```